

Manual to Load Image Data

Overview

SuperMap supports creating image cache for grid, image, and SIT files stored in UDB, ORACLE, SQLServer databases that already have image pyramids. Image cache is tiles for image data, which can optimize the publishing at the server side and browsing performance at the client side. Then SuperMap iClient3D for WebGL (abbreviated as WebGL Client) can access 3D services published by SuperMap iServer, and load image data.

This document explains how WebGL Client load and browse image data.

1. [Build Cache Data](#)
2. [Publish 3D Services](#)
3. [Load Image Data at Client Side](#)

Operations

Here is an example to illustrate the steps.

1. Build Cache Data

Introduction

Use SuperMap iDesktop to build 3D image cache file *.sci3d for the image data, which will be helpful for 3D service publishing.

Basic Steps

1 Open SuperMap iDesktop, Workspace

Manager>Datasource>Open File Datasource.

2 Select the grid dataset to generate cache, right click to display the context menu, click Create Scene Cache.




Fig. Create Scene Cache

3 In the dialog box that displays, as shown below:




Fig. Create Scene Cache dialog box

4 Add Datasets: Click Add Dataset to select the datasets for creating cache, click OK.

- Cache Type: Image.
- Tiling Type: Global.

5 For Parameter Settings, please follow the suggestions below:

- Cache Name: Input cache name, with default being dataset name@datasource name.
- Cache Path: The output path of the cache.
- Storage Type: Compact is suggested.

The Compact storage type compress and encrypt the data when caching, while the Original type keeps the original information.

- Picture Type: **JPG, PNG, JPG_PNG** are optional. WebGL Client does not support DXTZ.
- Tile Type: Select Global to generate *.sci3d cache.
- Tile Size: The resample size for generating tiles after caching. The unit is pixels*pixels. The default is 256*256.

Eight options are provided: 2048*2048, 1024*1024, 512*512, 256*256. You can choose the size based on your needs.

- Set password according to your needs.

6 Keep Cache Extent and Scales by default. Click OK to generate cache.

Results

A *.sci3d configuration file will be generated at the specified output path. Moreover, there will be a folder created to store image data, as shown below.




Fig. Results

2. Publish 3D Services

Introduction

After creating cache, we will see how to publish the image cache as 3D services to allow WebGL Client to load image data.

Basic Steps

1 Open SuperMap iDesktop, Workspace Manager>Scene>New Spherical Scene.

2 Layer Manager>General Layers>Add Image Cache Layer, select the *.**sci3d** configuration file generated.




Fig. Add image cache to scene

3 After adding cache layer, save the scene and workspace.

4 Start iserver via **startup.bat** under %SuperMap iServer_HOME%/bin.

5 Start browser, enter Web Manager

via <http://localhost:8090/iserver/manager>. Quickly publish a service at Home Page.




Fig. Quickly publish one or multiple services

6 In the Quickly publish service--Select datasource page, select the Workspace as the Data source, and click Next.



Fig. Select the Workspace as the Data source


7 In the Quickly publish service--Configure data page, click Remote Browse to select the workspace, click Next.



The screenshot shows a dialog box titled "快速发布服务-配置数据" (Quickly publish service-Configure data). It contains three input fields: "工作空间类型" (Workspace type) with a dropdown menu set to "文件型" (File type); "工作空间路径" (Workspace path) with a text box containing "F:/SampleData/Cache/Zh" and two buttons, "本地浏览..." (Local browse...) and "远程浏览..." (Remote browse...), where "远程浏览..." is highlighted; and "工作空间密码" (Workspace password) with an empty text box. At the bottom right, there are three buttons: "上一步" (Previous step), "下一步" (Next step), and "取消" (Cancel), with "下一步" highlighted.

Fig. Select the workspace

8 In the Quickly publish service--Select service type page, Select REST 3D Service, click Next.



The screenshot shows a dialog box titled "快速发布服务-选择发布的服务类型" (Quickly publish service-Select service type). It contains a text box stating "当前数据源支持以下服务类型，可多选。" (The current data source supports the following service types, multiple selections are allowed). Below this, there is a list of service types with checkboxes and dropdown arrows: "选中/取消选中" (Selected/Canceled), "REST-地图服务" (REST-Map service), "REST-数据服务" (REST-Data service), "REST-三维服务" (REST-3D service), "REST-空间分析服务" (REST-Spatial analysis service), and "RFST-交通网络分析服务" (RFST-Traffic network analysis service). The "REST-三维服务" checkbox is checked.

Fig. Select REST 3D Service

When finished, click Finish and Close.

Results

The service displays in the service

list <http://localhost:8090/iserver/services>, as shown below.



Fig. The published service

3. Load Image Data at Client Side

Introduction

After publishing service, WebGL Client can load the image data.

Please place WebGL package at %SuperMap
iServer_HOME%/webapps.

Basic Steps

1 Get the url of the 3D data.

- Enter <http://localhost:8090/iserver/services> and find the published 3D service.
- Enter root directory page, click realspace.
- Enter 3D page, click datas.
- Enter datas page, click links below.
- Enter data page, copy the address of the url.




Fig. Copy url address

2 Enter WebGL package in **%SuperMap iServer_HOME%/webapps**, open **terrainAndImagery.html** in text editor under the examples folder, change the address in SuperMapimageryProvider() to the address we just copied, as shown below.

```
function onload(Cesium) {
    var viewer = new Cesium.Viewer('cesiumContainer', {
        terrainProvider : new Cesium.CesiumTerrainProvider({
            url : 'http://www.supermapol.com/realspace/services/3D-zf_tin_image_z/rest/realspace/datas/info',
            //url : host + '/iserver/services/3D-zhufeng/rest/realspace/datas/info',
            requestWaterMask : true,
            requestVertexNormals : true,
            isSet : true
        })
    });
};
```

Fig. Change parameter

3 Open the **terrainAndImagery.html** page, that is, enter the url <http://localhost:8090/%WebGL>

[Package%/examples/terrainAndImagery.html](#) in the browser.

Results

After you open the page, the camera flies to the position of the image data, as shown below.




Fig. Image loaded at WebGL Client

Note: For more information about how to load terrain data, please refer to [Load Terrain Data](#).

Copyright© 2000-2017 SuperMap Software Co., Ltd.